## **Table of Contents**

Installing FreeNAS 9.10 .		1
---------------------------	--	---

## **Installing FreeNAS 9.10**

Start by powering down the server if it isn't powered down already.

Insert the bootable FreeNAS 9.10 installation USB stick and switch on the server.

If all goes well you will eventually be presented with the GNU GRUB screen.

Hit the "Return/Enter" key or wait for the counter to reach zero (shown in a red circle in the screen shot) and the process will start automatically.

1	Java iKVM	Viewer v	1.69.25 [	192.168.0.	2] TestSer	rver - Reso	olution 720 X 40	00 - FPS 35		_ 🗆	X
Vi	rtual Media	Record	Масго	Options	User List	Capture	Power Control	Exit			
				GNU	GRUB	version	2.02~beta2				26
	*FreeNAS	Insta	ller								
	Use Pres befo The hig	the 1 a s enter re boo hlighte	and ↓ 1 r to bo ting oi ed enti	keys to bot the r`c'fo ry will	select selecto or a con be exen	which e ed OS, mmand-1 cuted au	entry is hig 'e' to edit ine. Itomatically	yhlighted the comm y in 13s.	ands		

The FreeNAS console setup screen will appear.

Navigate around it using the " $\leftrightarrow \rightarrow \uparrow \downarrow$ " keys and to activate your choice hit the "Return/Enter" key.

Chose option 1 "Install/Upgrade" (1), select "OK" (2) and press the "Return/Enter" key.

🛓 Java iKVM V	/iewer v1	1.69.25 [	192.168.0.	2] TestSer	ver - Reso	olution 720 X 4	00 - FPS 30	
Virtual Media	Record	Macro	Options	User List	Capture	Power Control	Exit	
		fre	ieNAS 9	. 10-KELE	ASE CO	isole Setup		
			1	Beboo	t Sust	an		
			4	1 Shutd	lown Sy:	stem		
		2 (	K DK	>>		(Cancel>		

Now select the storage device you want the FreeNAS OS installed on (in Fester's case it's the SSD drive). Do not chose any of the HDDs you intend to use for your data, the FreeNAS OS cannot reside on any of the data storage disks (in Fester's server that is any of the WD40EFRX HDDs).

🋓 Java iKVM	Viewer v1	.69.25 [1	92.168.0.2	] TestSe	erver - Res	olution 72	20 X 40	00 - FPS 33		_ 0	X
Virtual Media	Record	Macro	Options	User List	Capture	Power Co	ontrol	Exit			
			Choo	se des	tinatio	n media	-			1	
	Select	led (us	r more ( se arro	drives w keus	where to nau	freeNAS igate t	shou o the	ild be e driue(s	:)		
	for in	stalla	tion; s	elect	a drive	with t	he sp	acebar)	•		
		1 adaØ	Samsu	122 m	850 PR	0 256GB		238 5 Gil			
	- t	J und		DC HD4	OFFRY-6			3013 (11			
	L L	] da1	ATA W	DC WD4	ØEFRX-6	8W 3	.6 Ti	i B			
		] da2	ATA W	DC WD4 DC WD4	ØEFRX-6	ow 3 8₩ 3	.6 Ti	i B			
	I	1 da4	ATA W	DC WD4	ØEFRX-6	8W 3	.6 T	iB			
	L I	l da5	ATA W.	DC WD4 DC WD4	ØEFRX-6 ØEFRX-6	8W 3 8W 3	.6 Ti	i B i B			
	Ĺ	1 da7	ATA W	DC WD4	ØEFRX-6	8W 3	.6 T	iB			
									4		
			K OK	>	<c< td=""><td>ancel&gt;</td><td></td><td></td><td></td><td></td><td></td></c<>	ancel>					
	<u></u>										

With the drive of your choice selected press the "Space Bar" key and an asterisk should appear next to the selected drive (1) now select "OK" (2) and press the "Return/Enter" key. If you want to install to two mirrored USB sticks, select them both and the installer will create the mirror.

🛓 Java iKVM	Viewer v1.69.25 [192.168.0.2] TestServer - Resolution 720 X 400 - FPS 29
Virtual Media	Record Macro Options User List Capture Power Control Exit
	Choose destination media Select one or more drives where FreeNAS should be installed (use arrow keys to navigate to the drive(s) for installation; select a drive with the spacebar).
	1       1
	2 Cancel>

If you see the following screen (it will only appear if FreeNAS has previously been installed on your boot device), select "Fresh Install" on the next screen and hit the "Return/Enter" key.



A warning screen will now appear, just select "Yes" and press the "Return/Enter" key.

🛓 Java iKVM Viewer v1.69.25 [192.168.0.2] TestServer - Resolution 720 X 400 - FPS 35
Virtual Media Record Macro Options User List Capture Power Control Exit
WARNING:
<ul> <li>This will erase ALL partitions and data on ada0.</li> <li>You can't use ada0 for sharing data.</li> </ul>
NOTE:
- Installing on flash media is preferred to installing on a
Proceed with the installation?
<pre></pre>

The next screen will ask you to create a login password for accessing FreeNAS. This is the final installation so a strong password (1) is recommended (you can change it later in the FreeNAS web GUI), just make sure you remember it.

Now press the "Tab" key, this should take you to the "Confirm Password" section and re-enter your password (2).

Press the "Tab" key again and this should take you to the "OK" section (3), press the "Return/Enter" key and the installation should begin.



When the installation is complete you should see a screen like this. Power off the server and remove the USB stick.



Now power up the server and the first screen you encounter will be the GNU GRUB screen, don't press any keys just wait a few seconds and it will automatically continue booting up FreeNAS.

When FreeNAS has finished booting you should see a screen like this with the IP address of the FreeNAS web GUI on display (shown in red in the screen shot).

(There are 4 IP addresses on Fester's screen because there are 4 NICs on the motherboard, and he has them all plugged in. This isn't ordinarily a good configuration-only plug in one NIC.)



Make a note of the IP address/s for the FreeNAS web GUI, it will be needed soon.

That's FreeNAS 9.10 installed now we need to configure it.

(By using IPMI or looking it up in your router's attached devices table, you will always be able to find the FreeNAS web GUI even if it changes.)

