

Table of Contents

Settings for System -> General 1

Settings for System -> General

Go to the “System” page (1) and click on the “General” button (2).

The screenshot shows the FreeNAS web interface. At the top, there's a horizontal navigation bar with icons for Account, System (circled in red with a red '1'), Tasks, Network, Storage, Directory, Sharing, Services, Plugins, Jails, Reporting, and Wizard. Below this is a secondary navigation bar for the 'System' page, with tabs for System, Information (selected), General (circled in red with a red '2'), Boot, Advanced, Email, System Dataset, Tunables, Update, CAs, Certificates, and Support. The main content area is titled 'System Information' and contains the following data:

Hostname	[REDACTED]	Edit
Build	FreeNAS-9.10-RELEASE (2def9c8)	
Platform	Intel(R) Xeon(R) CPU E5-2620 v3 @ 2.40GHz	
Memory	16248MB	
System Time	[REDACTED]	
Uptime	[REDACTED]	
Load Average	0.00, 0.06, 0.13	

- In the “General” page select “HTTP” (1) from the “Protocol:” drop down menu if it isn’t already selected.
- There is no certificate at this stage.
- Select the static IP address you want the FreeNAS web GUI to bind to from the “WebGUI IPv4 Address:” drop down menu (2). If you want to be able to get the FreeNAS web GUI on any static IP address you have assigned to the server then select 0.0.0.0 at this point. Ordinarily you should leave this set to 0.0.0.0.
- Leave the WebGUI HTTP port value and the HTTPS port value at their default settings (3).
- Select the language you require in the “Language (Require UI reload):” drop down menu (4).
- Pick a keyboard layout that corresponds to your keyboard in the “Console Keyboards Map:” drop down menu (5) (Fester’s keyboard layout corresponds to the UK so I use UK ISO-8859-1).
- Choose the correct time zone for your locality from the “Timezone” drop down menu (6).
- Now click the “Save” button (7).

Account System Tasks Network Storage Directory Sh

System Information General Boot Advanced Email System Dataset

Protocol: HTTP 1

Certificate: -----

WebGUI IPv4 Address: 192.168.0.5 2

WebGUI IPv6 Address: ::

WebGUI HTTP Port: 3

WebGUI HTTPS Port: 4

WebGUI HTTP -> HTTPS Redirect: ⓘ

Language (Require UI reload): English 5

Console Keyboard Map: United Kingdom ISO-885 6

Timezone: Europe/London 7

Syslog server:

Buttons: Save 7 Factory Restore Save Config Upload Config NTP Servers

From:
<https://www.familybrown.org/dokuwiki/> - danb35's Wiki



Permanent link:
<https://www.familybrown.org/dokuwiki/doku.php?id=fester:systemgeneral>

Last update: **2016/06/11 13:07**